

ATM Version 5.0 License Key Request and Installation Procedure

ATM License Key Request

A license key must be requested through the ISE Help Desk prior to installing or upgrading to ATM Version 5.0 or later. License keys are generated with a date of expiration 1 year from Annual License Fee Date. Messages indicating that the licenses will expire are generated in QSYSOPR 60 days prior to the License key expiring.

Please send all requests to help.desk@ise-erp.com or 1-888-473-0800

Required Information

The following information should be included in the license key request:

Company Name:	_____
Contact Name:	_____
Street Address:	_____
City, State Zip	_____
Phone #:	_____
Fax#:	_____
iSeries Make/Model:	_____
iSeries Serial Number:	_____
Product Code:	5ATMAPL
Product Identifier:	5101
Number of Users:	_____

Applying License Keys to the iSeries

- Once the installation is complete from a command line type the following: WRKLCINF and prompt with “F4”
- Enter 5ATMAPL into the product identifier field and press enter
- Enter a 1 next to Feature Code 5101 and press enter
- Type in the information contained in the license key text file emailed from the ISE Help Desk and press enter.

Session A - [24 x 80]

File Edit View Communication Actions Window Help

Add License Key Information (ADDLICKEY)

Type choices, press Enter.

License key input	> *PROMPT	*PROMPT, *LICKEYFILE, *TAPE
Product identifier	> 5ATMAPL	Identifier
License term	> V2	Vx, VxRy, VxRyMz
Feature	> 5101	5001-9999
System serial number	> 105L7LM	Number, *LOCAL, *REMOTE, *ALL
Processor group	> <u>ANY</u>	Character value, *ANY
License key:		
Characters 1 - 6	_____	Character value
Characters 7 - 12	_____	Character value
Characters 13 - 18	_____	Character value
Usage limit	> <u>1</u>	0-999999, *NOMAX
Expiration date	> <u>*NONE</u>	Date, *NONE
Vendor data	> <u>*NONE</u>	Character value, *NONE

Bottom

F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display
F24=More keys

MA a MW 10/037

1902 - Session successfully started